

ICT2201 Digital Forensics

NCMF User Manual

AY2021/2022, Trimester 1

Contents

| 1. | Introduction | 3 |
|-------|--|----|
| 2. | Prerequisites | |
| 3. | Set up guide | |
| | | |
| 4. | Running NCMF | 4 |
| 4.1 | Speech to Text Function | 7 |
| 4.1. | Providing only a single audio file | 7 |
| 4.1.2 | Providing a folder of multiple audio files | 7 |
| 4.2 | Image OCR Function | 8 |
| 4.2. | 1 Text extraction on image files | 8 |
| 4.3 | Text file Function | 9 |
| 4.3. | Count the top 3 word occurrence & search for suspicious word list in a text file | 9 |
| 4.3.2 | Count the top 3 word occurrence in a text file | 9 |
| 4.3.3 | Search for suspicious word list in text files | 10 |

1. Introduction

This document is a detailed user manual and guide on how to use NCMF's Audio/Image Analyzer.

2. Prerequisites

Required software:

Python (at least v3.9)

Required Python libraries:

- > pydub
- SpeechRecognition
- > opency-python
- > Pillow
- pytesseract

Required files to install:

- > FFMPEG (Download the latest version from https://www.gyan.dev/ffmpeg/builds/)
- Tesseract (Download the latest version from https://github.com/UB-Mannheim/tesseract/wiki)

3. Set up guide

- 1. After FFMPEG and Tesseract installation, update your System Environment Variables as shown in Fig 1
 - a. Update System Variables' Path to include FFMPEG's bin folder file path and Tesseract installation path as shown in Fig 2
 - b. Restart the computer
- 2. Update tesseract variable with Tesseract.exe's filepath in software code as shown in Fig 3 at line 16 of ncmf.py (Note that the filepath may vary depending on where Tesseract has been installed in your computer)
- 3. Run the following commands to install necessary libraries and packages
 - a. pip install SpeechRecognition
 - b. pip install pydub
 - c. pip install opency-pythonz
 - d. pip install pytesseract
 - e. pip install Pillow




Fig 1




Fig 2

```
# Amend file path according to where you have installed tesseract.exe
pytesseract.pytesseract.tesseract_cmd = r'C:\Program Files\Tesseract-OCR\tesseract.exe'
```

Fig 3

4. Running NCMF

Start Page

To run NCMF, enter the following command in your terminal:

python ncmf.py

The NCFM's logo, help menu and some examples on how to use NCMF should be displayed.

Fig 4

Main Help Page:

To see the available arguments in NCMF, enter the following command in your terminal:

> python ncmf.py -h

You should see the options appearing with the various functions you can perform with NCMF. Refer to table 1 for detailed explanation of what each function does.

Fig 5

| Options | What it does |
|---------|---|
| - h | Used to display the help menu |
| - r | Used when users want to analyze a single audio file |
| - i | Used when users wish to analyze an image file |
| - S | Used when users want to specify their own word list for the search against suspicious |
| | words with their audio transcription result or image text extraction results. |
| - m | Used when users want to analyze multiple audio files residing in a single folder |
| - n | Used when users want to modify the amount of top word occurrences to be displayed |
| | in the text results. |

Table 1

Options for text-files:

NCMF supports analysis for text file as well in the event when users wish to check against a text file. To see the functions available for text file, type the following command in your terminal

> python ncmf.py o -h

Refer to Table 2 for detailed explanation of what each function does

Fig 6

| Options | What it does |
|---------|---|
| o -a | Used when users want to analyze text files with the 2 functions (Counter |
| | and Sus_words) |
| o -b | Used when users only want to analyze text files to obtain the top 3 occurring |
| | words in the file |
| о -с | Used when users only want to analyze text files to obtain suspicious words |
| | discovered in the search against the tool's default suspicious word list |

Table 2

4.1 Speech to Text Function

4.1.1 Providing only a single audio file

Step 1: Run the command 'python ncmf.py -r (filename)'

Step 2: Results are parsed in your current directory as printed by the tool

Fig 7. Sample command for Single Audio file

4.1.2 Providing a folder of multiple audio files

Step 1: Save all audio files into a single folder and save the folder into the directory with ncmf.py

Step 2: Run the command 'python ncmf.py -m (folder name)'

Step 3: You will be prompted to enter a name for a new folder. All generated results will be saved in the new folder created in the current directory.

Fig 8. Sample output for Step 3

4.2 Image OCR Function

4.2.1 Text extraction on image files

Step 1: Run the command 'python ncmf.py -i (image name)'

Step 2: You will be prompted to enter a name for 2 files which will be saved in the current directory:

- 1. Image consisting of captured text
- 2. Text file with extraction results

Fig 9. Sample output for step 2

4.3 Text file Function

4.3.1 Count the top 3 word occurrence & search for suspicious word list in a text file

Step 1: Run the command 'python ncmf.py o -a (text filename)'

Step 2: When the tool has finished the count and search, the results will be appended to the provided text file.

Fig 10. Sample output after tool has finished processing request

4.3.2 Count the top 3 word occurrence in a text file

Step 1: Run the command 'python ncmf.py o -b (text filename)'

Step 2: When the tool has finished the count, the results will be appended to the provided text file.



Fig 11. Sample output after tool has finished processing request

4.3.3 Search for suspicious word list in text files

Step 1: Run the command 'python ncmf.py o -c (text filename)'

Step 2: When the tool has finished the search, the results will be appended to the provided text file.

Fig 12. Sample output after tool has finished processing request